# LAKE COUNTY ELECTION DAY VOTING SYSTEM OPERATIONS MANUAL



D. ALAN HAYS, D.M.D.,
LAKE COUNTY SUPERVISOR OF ELECTIONS

www.lakevotes.com

hays@lakevotes.com

Phone: (352) 343-9734

Fax: (352) 343-3605

# **Table of Contents**

l.	EViD Operator Instructions	2
II.	Spoiled Ballots	5
III.	Found Ballot/Uncast Ballot	6
IV.	Provisional Ballots	7
v.	DS200 Scanner Operation	9
VI.	Emptying a Full Ballot Box	11
VII.	Clearing Jammed Ballots	12
VIII.	Non-Functioning Scanner	13
IX.	DS200 Startup / Shutdown	14
x.	ExpressVote Startup / Shutdown	17
XI.	Voting Process for ExpressVote	19
XII.	Voter Information Updates	21
XIII.	Clerk Opening Process	22
XIV.	Clerk Closing Process	24
XV.	EViD Name and Address Changes	26
XVI.	Undo a Check-in	31
XVII.	Appendix	32

## I. EViD Operator Instructions

This is an overview of the process. Please refer to the EViD Operator Checklist for specific open/close instructions. Checklist is found in the Clerk Binder.


 When a voter comes to your line, ask for a form of signature and photo ID (<u>Driver's License works best since it has both</u>). Verify picture ID is the same person standing in front of you. The address does not need to be correct for an ID to be acceptable.



Only the following forms of photo ID are acceptable by law:

- Florida driver license
- Florida ID card issued by the Department of Highway Safety and Motor Vehicles
- U.S. passport
- Debit/credit card
- Military ID
- Student ID
- Retirement center ID
- Neighborhood association ID
- Public assistance ID (Social Security or other social services)
- Veteran health ID card issued by the U.S. Department of Veterans Affairs License to carry a concealed weapon or firearm issued pursuant to section 790.06, Fla. Stat.
- Employee ID card issued by any branch, department, agency, or entity of the federal government, state, county, or a municipality.

- 2. Find the voter's name using either the date of birth search or ID swipe process.
- 3. Verify voter's date of birth and check for their name.
- 4. Ask voter to verify personal (name and address) information on Signature Pad is correct.
  - a. If an address change is needed, direct voter to the Clerk.
  - b. If a name change is needed, direct voter to the Clerk.
  - c. If a reinstatement is needed, process the voter.
  - d. If the voter's name does not come up on the EViD, double check the birth date was properly entered. If voter cannot be found, send voter to the Clerk for further investigation.
  - e. Always follow EViD ticket instructions.
- 5. If everything is current, have the voter sign the Signature Pad connected to the EViD.
- 6. Compare the signature on the ID to the signature displayed on the EViD screen. The signatures should be similar.
- 7. If signature is substantially similar, touch Accept Signature. A voting pass will print out.
- 8. Hand Voting Pass to Voter. Instruct voter to take Voting Pass to Ballot Issuer at next table.
- 9. Ballot Issuer will compare the <u>ballot style</u> on the face of the ballot and the **Voting Pass** to ensure the proper ballot has been issued.
- 10. Have voter compare the <u>ballot style</u> on the face of the ballot and the **Voting Pass** to ensure the proper ballot has been issued. For a complete ballot there could be more than one page.
- 11. Place the **Voting Pass** in the yellow "cheese box".
- 12. Give voter a short set of instructions:
  - a. Instruct the voter to use the ink pen provided in the privacy booth.



- b. Instruct the voter to mark their ballot selections by darkening the oval completely next to their choices. No "X"'s or "✓" marks.
- c. Instruct the voter to only make as many selections for each contest as the contest title indicates on the ballot.
- d. If there are any contests on the back of the ballot, tell the voter to vote both sides.
- e. If the voter asks if all contests need to be voted on, simply tell them the contests they skip will not be counted but all that are properly marked will be tabulated.
- 13. Place the ballot into the secrecy sleeve and hand it to the voter.
- 14. Instruct the voter to proceed to the privacy booth to complete their ballot.
- 15. If the voter wishes to change any selections, instruct them to see the Clerk for a new ballot. Erasures are not permitted.
- 16. When complete, the voter should place the ballot inside the secrecy sleeve then proceed to the ballot scanner and feed their ballot into the scanner.
- 17. An election worker must inspect all privacy booths after each voter finishes with their ballot. Check for anything left in the booth such as used sample ballots, fliers, notes or trash and remove them.
- 18. Watch for any voter who tries to leave the polling place without scanning their ballot. All ballots are to remain in the polling room.
- 19. During a lull, retrieve the secrecy sleeves from the Technician.



## II. Spoiled Ballots

- 1) If a voter makes a mistake or needs to make a change on their ballot, they must be sent to the Clerk for a replacement.
- 2) The voter will place the spoiled ballot in a **Spoiled Ballot Envelope** and seal the envelope. The
  Clerk will fill out the information on the envelope.
- 3) The Clerk will document this information on the **Spoiled Ballot Log**.
- 4) The Clerk will place the spoiled ballot envelope containing the ballot in the large envelope marked for **Spoiled Ballots**.
- Go to the Ballot Issuer table to retrieve a new ballot.
- 6) The Clerk will verify proper ballot style and hand it to the voter.
- 7) Inform the voter that they can only have three attempts to complete.

#### Note to Clerk:

A Vote-by-Mail ballot that is turned in (Cancelled) at the polling place is not counted as a Spoiled Ballot and does not need to be logged on the **Spoiled Ballot Log**. This voter can then vote a regular ballot.

Vote-by-Mail ballots cannot be dropped off at the Election Day polling place.

- 8) Inform the voter to only vote for the number of candidates indicated in the title of the contest.
- 9) Tell the voter to proceed to the privacy booth to complete the replacement ballot.
- 10) When finished the voter proceeds to the scanner to cast the ballot.

REMEMBER! If a ballot has been scanned and has dropped into the ballot box there will not be another ballot issued even if the voter says they made a mistake on the ballot.

# III. Found Ballot / Uncast Ballot

#### If a ballot is found in or around the polling place but not put through the scanner, this procedure should be followed;


- Verify that the ballot is not a sample ballot.
- 2. Verify that it is not a Vote-By-Mail ballot (the ballot will have been folded from being sent through the mail).
- 3. Once it is determined to be an actual Election Day ballot, collect the ballot and bring it to the Clerk's table.
- 4. Clerk will place ballot in an envelope marked "Found / Uncast ballot".
- Envelope will be placed in the Supply Tote.
- 6. A call must be placed to the Elections Office explaining that a ballot was found.
- 7. When Clerk drops off supplies, the Found/Uncast ballot must be given to Zone Courier for immediate delivery to the Elections Office.



## IV. Provisional Ballots

When a voter comes in to vote, and the EViD has flagged that person to vote a provisional ballot, or they have no identification, or they dispute their ineligibility, these steps should be followed;

- You (as the Clerk or Assistant) have received a Refer to Clerk ticket that the voter must vote a provisional ballot, or they have presented no identification or insist on voting.
- 2. Clerk should fill out (in its' entirety) the Provisional Ballot Certificate Envelope and mark the reason(s) on the back.
- The <u>Clerk and voter MUST SIGN</u> the Provisional Ballot Certificate Envelope.
- 4. Once the Provisional Ballot Certificate is completed the Clerk will input the certificate number into the EViD and let the voter sign on the signature pad.
- 5. Once the information has been put into the EViD a **Voting Pass** will print, paper clip (or tape) to Provisional Ballot Certificate Envelope.
- Give the information stub from the Provisional Ballot Certificate Envelope to the voter. Tell the voter they can call the number on the stub or visit our website to see if their ballot was counted after the election.
- 7. Complete a Multi-Purpose Form in its entirety. **Make sure voter signs form.** Paper clip Multi-Purpose Form to Provisional Ballot Certificate Envelope.
- 8. Issue the voter the correct ballot style and the Provisional Ballot Certificate Envelope and Provisional Ballot Secrecy Sleeve (do not give the provisional voter a manila folder secrecy sleeve).
- 9. Instruct the voter to complete the ballot at the Clerk's privacy booth (always setup booth next to Clerks table). <u>Inform the Technician that the provisional ballot is not to be scanned.</u> The voter should place the ballot in the Provisional Ballot Secrecy Sleeve and then place it in the Provisional Ballot Certificate Envelope and seal it.



**Provisional Ballot Certificate Example** 

- 10. The voter should return the sealed envelope directly to the Clerk.
- 11. Verify the Provisional Ballot Certificate Envelope is **completely and correctly** filled out before voter leaves the precinct. Make sure **each line is filled out** or use N/A.
- 12. Clerk will fill out Provisional Ballot Log after each completed Provisional Ballot Certificate Envelope and rubber band it to the completed ones.

		PΜ			-1. A.A	
	11/3/20	4:58 PM	RJ	555	Eligibility cannot be determined	,
1407.2	11/3/20	5:40 PM	RJ	556	Eligibility cannot be determined	
1A07.2	11/3/20	6:20 PM	RJ	557	Eligibility cannot be determined	1
1407.2	11/3/20	6:59 ₽M	RJ	558	Eligibility cannot be determined	1
			End of da	av harcode se	al number 2304	
			Lilu oi ue	ay barcode se	ai number	

PROVISIONAL BALLOT LOG

- 13. The Clerk will place the completed certificates (rubber banded) in the blue **Provisional Ballot Box/Bag** for safekeeping.
- 14. Rubber band all completed **Provisional Ballot Certificate Envelopes with the Provisional Ballot Log.**
- 15. Retrieve a zip tie from the Provisional Ballot Bag and apply to the Provisional Ballot Bag after every completed Provisional Ballot Certificate Envelope is placed in the bag.
- 16. Take the **Provisional Ballot Box/Bag** to drop off location at the end of Election Day.



# V. DS200 Scanner Operator Instructions

- 1. Make sure the voter's ballot is in the secrecy sleeve before they approach the scanner.
- 2. All voters MUST be allowed to cast a secret ballot. Do not view a voter's ballot.
- 3. When the scanner is ready for a ballot it will read "Welcome. Please Insert Your Ballot". The Public Count is displayed at the top of screen. On a multiple piece ballot, the public count will only advance on the first page.
- 4. **For every voter**, make them aware of the public count prior to scanning their ballot. Point out that the public count number will advance by one for every proper ballot cast during Election Day.
- 5. Simply tell the voter to insert the ballot into the scanner in any direction. The scanner will pull the ballot in and drop it into the ballot box. After the voter scans the ballot, they can hand you the secrecy sleeve.
- 6. Verify the ballot has fallen into the ballot box. After each ballot, check the back-viewing window to ensure the ballot has fallen and is not stuck in the back. If there is a ballot stuck in the feed path, usually a simple bump will allow it to fall. In most cases you can hear the ballot drop and hit the bottom of the ballot box.
- 7. If the scanner beeps, use the secrecy sleeve to cover and block your view of the ballot. Read the message then check the following:
  - a) **Is there a ballot jam?** Pull the ballot out gently and let the voter reinsert the ballot straight into the scanner.
  - b) **Is the ballot blank?** The scanner will stop if there is "No Votes Detected on Ballot". The screen will display "Return" or "Cast Blank

#### **REMEMBER:**

Position yourself far enough away from the scanner so there is no way to view a voter's ballot.

Make sure the cardboard catch box (if issued) is in the bottom of the DS200 ballot bin.

Once a ballot drops into bin, regardless of screen message, the ballot should never be retrieved from the bin.

Never allow a voter to scan a provisional ballot or a vote by mail ballot.

Ballot". Allow the voter to decide what action will be taken and to make their selection on the screen.

- i. If the voter presses "Cast Blank Ballot", the ballot will be dropped in the ballot box and the voter is finished.
- ii. If the voter presses "Return", the ballot will be returned to them. The voter should be directed back to the privacy booths to complete the ballot. The voter can then insert their completed ballot into the scanner.
- c) Are there too many selections on one contest? The scanner will stop if there are over votes. The screen will display "Accept" or "Return". Allow the voter to decide what action will be taken and to make their selection on the scanner.
  - If the voter presses "Accept", the ballot will be dropped in the ballot box and the voter is finished. The over voted contest will not be tabulated. All other contests will be counted.
  - ii. If the voter presses "Return", the ballot will be returned to them. They will go to the Clerk to have that ballot spoiled and a replacement ballot issued to them.
- 8. When the scanner has an issue, read what the screen has displayed. It will not allow you to feed a ballot until the corrective action is completed and the screen reads "Welcome. Please Insert Ballot".
  - a. <u>Important</u>: If the jam occurs past the scanner, <u>read the screen</u> <u>carefully</u>. The display will state if the ballot was read or not. That will determine if the ballot will be re-scanned if not read or pushed through to the ballot box if jammed after the ballot was read.
- 9. When the scanner successfully reads a ballot, the screen will read, "You Are Finished Thank You for Voting."
- 10. All ballots MUST remain in the polling place. Always be on the lookout for a voter that has not scanned their ballot and is walking out of the polling place.

## VI. Emptying a Full Ballot Box

Any access to the DS200 ballot box will be a two-person process, one of which MUST be the Clerk.

<u>During voting hours</u>, the Ballot Box Access Log (located in the Affirmation Folder) must be filled out prior to opening the ballot box door.

- 1) If the public count has reached 1,000 during voting hours, it will need to be emptied.
- 2) Unlock the ballot box and open the door.
- 3) Remove the catch box from the ballot box of the DS200. Take out and straighten the ballots. The ballots do not need to face the same way. Place ballots in a carboard box from the supplies.
- 4) Return the catch box to the ballot box of the DS200.
- 5) Lock the ballot box door.
- 6) Tape the carboard box with tape provided in the supplies.
- 7) Store the taped box in the Ballot Transfer Bag.
- After the polls are closed, remove tape from taped box place the remaining ballots from the ballot box and place into the same cardboard box, keeping the ballots from each respective DS200 in the corresponding cardboard box.

## VII. Procedure for clearing Jammed Ballots

#### Determine where the ballot jam is located.

Use the **Secrecy Sleeve** to cover and block the view of a ballot that needs to be removed from a jam.

- 1. If jam is in the feed path inside the ballot box:
  - a. Unlock and open the ballot box door.
  - b. Pull ballots from the upper-rear feed path so ballots will fall free into ballot box.
  - c. Lock ballot box door when jam is cleared.
- 2. If jam is in the feed path of the scanner:
  - Unlock the front scanner door then fold the door down.
  - b. Pull the scanner towards you enough to see behind the machine.
  - c. Grab and hold the ballot so it does not fall directly into the ballot box.
  - d. The ballot may simply pull out. (If not proceed to next step)
  - e. Unlock and lift the cover to access the scanner read head.
  - f. Lift up on the two blue release tabs on each side of the scanner read head.
  - g. Remove jammed Ballot.
  - h. Close and lock back cover.
  - i. Push scanner back into position.
  - j. Fold door back up and lock front of scanner.
- 3. If jam is between the scanner and ballot box:
  - a. Unlock the front scanner door then fold the door down.
  - b. Slide the scanner towards you enough to clear the jammed ballot.
  - c. Slide scanner back into position and relock the front scanner door. Be sure not to pinch the power cord that connects to the back of the scanner.

#### **IMPORTANT!**

## ALWAYS READ THE DISPLAY SCREEN FIRST!

Be aware of whether the ballot jammed before it was scanned or after it was read.

It is important to always be aware of the public count before and after a voter has scanned their ballot.

If the public count has advanced by one, it has clearly been tabulated.

If the ballot box needs to be opened during voting hours, the Ballot Box Access Log must be filled out. This procedure requires two election workers.

# VIII. Procedure for Non-Functional Scanner

- 1. Call the Technical Help Desk.
- If your precinct only has one scanner and it is non-functional, cut the permanent seal and unlock the auxiliary bin cover so ballots can be inserted.
- 3. Inform the Clerk of the scanner issue and that there will be ballots in the auxiliary ballot bin.
- 4. Work with the help desk to determine why the scanner is not functioning properly.
- 5. If scanner becomes operational or is replaced, the Clerk and Technician will scan any ballots placed in the auxiliary bin.
- If it is determined that the scanner needs further attention or is to be replaced, the help desk will dispatch the closest Zone Courier to deliver and help set up a replacement scanner.

#### Important Notes

If you have 2 scanners use the working scanner until Tech Help arrives.

Always be aware of the public count and what the screen has displayed.

If for any reason the Clerk and Technician cannot scan a ballot(s) after the scanner has been repaired/replaced any voted ballots that are contained in the auxiliary bin will be placed in the bottom trunk of the ballot transfer bag. When finished with the polling place close down, the ballot transfer bag will be delivered directly to the election's office by way of the Zone Courier.

- 7. The Technician will remove the thumb drive from the original scanner and place it in the new scanner. The scanner that needs repair will be returned to the Election Office via the Zone Courier.
- 8. If the election equipment needs to be removed from the polling place, an **Election Equipment Change of Custody** form in the **Affirmation Folder** will need to be filled out to document all serial number changes including the new scanner serial number.

Rev. 06/17/20

9. The Clerk will document the occurrence on the Incident Report Form.

## IX. DS200 Startup / Shutdown

#### **DS200 Startup DS200** 1. Using the "Precinct Report Form", verify and remove the two TOP HATCH security seals. (Top hatch and ballot box) The auxiliary bin will remain sealed. **DS**200 Assist the Clerk to remove the ballots and any other supplies from the ballot box. 3. Unlock and open the back door that holds the power cord. Plug in to a wall outlet. This door **AUXILIARY BIN** will remain open while the scanner is plugged in all day. **BALLOT BOX** 4. Open the top latches to gain access to the DS200 scanner. Push down on top to ease turning the key. 5. Unlock the screen on the DS200 and raise the LCD screen. The scanner should power up automatically. This will take a couple minutes. If your DS200 does not power up automatically, unlock the access door covering the power button -- Press the power button to turn on the DS200. The DS200 will take a couple of minutes to initialize. The scanner will then print a Configuration Report. 6. Enter the Election Code (we will provide the code in your folder and/or Clerk Binder). 7. On the next screen press **Open Poll**. 8. The Ballot Status Accounting report prints automatically after the Configuration Report and Zero Totals Report. Any Election Board member can sign the Zero Totals Report. Place (signed) tapes in labeled Ziploc bag.

	<ol> <li>After the reports finish printing, press Go to Voting Mode to continue opening polls.</li> </ol>	
	10. You are now ready to begin scanning ballots.	Tips for the day
	<ol> <li>Check screen for ballot issues or system messages and errors.</li> </ol>	Station yourself close to each scanner and instruct each voter to feed the ballot in the
	END OF DS200 STARTUP	scanner in any direction. For a multiple piece ballot scan the first piece then the second.
<b>DS20</b>	0 Shutdown	Point out the public count number to each voter. Inform
	<ol> <li>Open the access door and press the Close Polls button.</li> </ol>	the voter it will advance by one when the ballot is scanned. For a two-piece
	2. Press the <b>Close Polls</b> button on the screen.	ballot both pieces must be scanned.
	Then the system will automatically print the results reports.	Explain any messages that appear on the screen. Allow
	<ol> <li>On the next screen select Begin Modem Process.</li> </ol>	the voter to make the decision to return ballot or cast ballot as marked.  Technician shall not press
	4. The scanner will attempt to connect to the server and will show on the screen when it is connected.	any on screen buttons for voter.
	5. When the results have been sent successfully <b>pr</b>	ess OK.
	6. Select Finished – Turn Off.	
	7. Remove the USB thumb drive when the Power	light is off.
	8. Call the Tech Help Desk to verify results were re	eceived.
	9. Election Board will <b>sign all signature lines</b> on re	esults tapes.
	10. Tear results report under first set of signature line Precinct Report Form accounting.	es. Retain top portion for
	11. Tape bottom signed portion of results report to fre place.	ont entrance of polling
	12. Place the tape in the <b>Ziplock bag</b> along with the	other printed reports.
	13. Assist the Clerk with removing all voted ballots from them in the properly marked black ballot bag and	

of the DS200 will be on the tag. Sign and record the public count on the black transfer bag tag. Have the clerk sign the tag also.
14. After ballot accounting, place all <u>unused</u> ballots back in the cardboard boxes. Then, place them back in the ballot box.
15. Return all Secrecy Sleeves and extension cords to the ballot box.
16. When complete, lock and seal the scanner and ballot box. Lock the back door that houses the power cord. Document the numbers on the <b>Precinct</b> <b>Report Form</b> .

#### **END OF DS200 SHUTDOWN**

# X. ExpressVote Startup / Shutdown



### **ExpressVote Startup**

1.	After removing the seal from the ExpressVote carry bag, set up the ExpressVote. Preferably this should be on a table. <b>Plug it into a power outlet</b> .
2.	Position the ExpressVote in a location to offer privacy in the polling place and setup the privacy screen.
3.	Plug the small circular end of the power cord into the port on the back of the ExpressVote. Flat side up.
4.	Plug the male end of the cord into the wall outlet.
5.	Have the headphones available next to the machine.
6.	Verify the navigation pad is attached to the side of the machine.
7.	<b>Unlock the security access door</b> on the side of the machine using the DS200 keys.
8.	Verify that the <b>thumb drive</b> is installed, and verify the switch is on <b>Voter</b> mode, verify the navigation pad is plugged in.
9.	Turn the power switch to the on position.
10.	Close and lock the security access door. The screen will light up and start to load.

	11.	Apply security seal to the security access door. There is a place to apply a security seal at the base of the security access door.
	12.	A screen will read Insert Media/Calibrate. Please do not touch the screen until the Enter the Election Code screen comes up.
	13.	<b>Enter the Election Code</b> (we will provide the code in your folder and/or Clerk Binder) on the next screen.
	14.	On the next screen, <b>Verify the Precinct</b> number is correct, and touch <b>OK</b> at the bottom of the screen.
	15.	Now the ExpressVote is ready for the first voter.
		END OF EXPRESSVOTE STARTUP
Expre	essV	<u>/ote Shutdown</u>
	1.	After polls close and last voter votes, retrieve the Access Door Key.
	2.	<b>Cut security seal</b> from <b>security access door</b> , and place in labeled Ziploc bag.
	3.	Unlock the access door and flip the power switch to off.
	4.	Once the ExpressVote is in the off position, the thumb drive may be removed and placed in the labeled Ziploc Bag.
	5.	Keep the keypad connected, close and lock the access door and remove the key.
	6.	Unplug the headphones if used. <b>Unplug the power cord</b> from the wall outlet and remove it from the machine. Place the ExpressVote and all items in the carry case. Place unused ballot cards in ExpressVote carry case as well.

#### **END OF EXPRESSVOTE SHUTDOWN**

# XI. Voting Process for ExpressVote

1.	Voter is first checked in at an EViD station.
2.	Tech collects voting pass and uses it to input info for correct ballot. When
	completed give Voting Pass to Clerk
3.	Tech begins by going to the ExpressVote. "To begin voting insert your
	card" should be displayed on the screen.
4.	Insert an unmarked ExpressVote ballot card into the input slot.
5.	When the <b>Precinct Selection: Search</b> screen appears, select search to
	view a list of all the available precinct choices.
6.	Select the correct precinct on the <b>Precinct Select: Results</b> screen.
7.	If the selected precinct has a single ballot style the system displays the
	Confirm Selections screen.
8.	If the selected precinct has multiple ballot styles, the system displays the
	ballot style selection screen.
9.	Select the correct ballot style (see Voting Pass for information).
10.	On the Confirmation Selections screen, examine your precinct and ballot
	style choices. If selections are correct, select <b>Activate</b> to activate the ballot
	on the ExpressVote.
11.	If applicable, select a <b>Language</b> if multiple languages are available.
12.	The voter begins at this point. The voter may use the buttons at the bottom
	of the screen to access display options and navigate the screen (Previous,
	Zoom, Exit, Contrast, and Next).
13.	Select a candidate or contest choice by touching the oval or anywhere on
	the line.
14.	The selection will be highlighted in yellow, and a check mark will appear
	next to your selection.
15.	To change a selection, simply touch the new choice.

16.	For "multiple vote for" contest, simply de-select the incorrect choice and
	touch new choice.
17.	A "Write In" option may be available, if voter desires to write in a candidate
	simply use the onscreen keyboard to input.
18.	Under-votes will be identified, and voter will be informed.
19.	The ExpressVote will ask the voter to <b>Verify Selections</b> .
20.	Upon completion of all contest selection(s) the ExpressVote prints the
	ballot. The ballot is brought to the DS200 for tabulation inside of a secrecy
	sleeve.
21.	To cancel a voting session (voter leaves the precinct and decides not to
	vote), the Tech must touch the top left corner of the screen (the blue area
	on the top of the screen-no button is present but it is an active area). Then
	follow the screen instructions to end the session.
22.	The Express Vote is now ready to accept the next voter.

# XII. Voter Information Updates

- ☐ If a voter receives a **Refer to Clerk** ticket you can update the following at the Clerk's station:
  - Name Changes
  - Address Changes
  - Signature Updates

ANY VOTER UPDATE MUST BE DOCUMENTED WITH A FULLY COMPLETED AND SIGNED MULTI-PURPOSE FORM.

- ☐ If a voter has moved from another Florida county where they were properly registered:
  - Call the SOE Office, they will transfer the voter's record to Lake County. This will take a few minutes.
  - Complete a Multi-Purpose Form while waiting for the information update.
  - When information is updated, you will be able to process voter as normal.

# XIII. CLERK OPENING PROCESS

1. Be at the assigned precinct by 6:00 am.
2. Remove supplies that are needed from supply tote.
3. <u>Setup Verizon Jetpack MIFI located in Clerk's EViD case and setup and start Clerk EViD</u> . Leave on Clerk's table all day.
4. Delegate and help set up all voting equipment, tables and chairs.
5. Retrieve the Precinct Report Form (PRF) from the Clerk's binder and verify the correct seal numbers are still intact on the DS200, ExpressVote, and EViDs before the Technician starts the opening process. Keep ALL USED SEALS – place all seals in labeled Ziploc in supply tote.
6. Remove all ballots, extension cords, and secrecy sleeves from the DS200 ballot box. Make sure you have the correct ballot styles and numbers that were delivered to your precinct as stated on the PRF.
7. Compare the sample ballot information to the Election Day ballots (candidates, referendums, charter amendments, if applicable). <a href="NOTE">NOTE</a> : Sample ballot is on top on Election Day ballots, compare the information only, not the style number.
8. Make sure the Poll Deputy displays all issued precinct signs for passing motorists. The Poll Deputy uses the 150' No Solicitation Zone Arial Image found in Clerk Binder to familiarize and mark (if appropriate) where the 150' zone is located.
9. Delegate the Election Workers to set up tables for the voter check-in and EViD setup.
10. Make sure all posters and sample ballots are displayed on tables so voters can see them as they approach the check-in tables.
11. Make sure EViD operators are familiar with the check-in process and EViD Voting Pass process (Election worker gives Voting Pass to voter, then sends voter to Ballot Issuer).

ш	by step setup instructions. Check seals to PRF.
	13. Make sure ballot issuers are familiar with looking at the EViD Voting Passes for the ballot style to determine the correct ballot to give the voter. The used EViD Voting Passes will be kept in a yellow container (Cheese Box) at the ballot issue table. The Ballot Issuer will verify the ballot style on the EViD Voting Pass. Display EViD Voting Pass and correct ballot allowing voter to verify before handing to him or her.
	14. Verify all workers have signed payroll sheet. Administer the oath for all Election Workers except the Poll Deputy. Oath is located on the top portion of the payroll sign in sheet. Keep the payroll sheets in the Clerk Binder for safe keeping.
	15. Sign the zero tapes from the DS200(s) then place them in the Ziploc bag provided for safe keeping. You will find the Ziploc bag for the tapes in the supply tote. You will also need this Ziploc bag after closing for the results tapes, and thumb drive(s).
	16. Once the polls open at 7:00 am the Technician will be the DS200 and ExpressVote operator.
	17. Verify all equipment is setup and operational before 7:00 am (EViDs, ExpressVote, DS200, etc.).
	18. Clerk utilizes personal cell phone time and announces polls open at 7:00 am.
	19. The Poll Deputy should <u>suggest</u> to approaching voters to have their photo and signature ID ready when they get to the check-in table. A driver's license is the best form of ID.
	20. Throughout the day start delegating tasks to prepare for closing the polls at 7:00 pm.

# XIV. CLERK CLOSING PROCESS

1. Once the Tech is finished closing and transmitting the results from the DS200(s) the thumb drive(s) will be removed and placed in the same Ziploc bag with the DS200 tapes and ExpressVote thumb drive. This Ziploc bag will be placed in the supply tote.	NOTE:  Clerks should delegate some task to ensure timely completion of duties after the polls close. All polling places are different; this list will help with closing the	
2. <b>EViD thumb drives</b> will be pulled after each machine is shut down. Cut the seal and place them back in a large labeled Ziploc bag and place in supply tote.	polls. Clerk will use personal cell phone for announcement of close of polls.	
3. Shut off Verizon Jetpack MIFI and repack in box. <a href="tote">tote</a> .	Place packed box in supply	
4. Remove all voted ballots from the ballot box and p transfer bag (top compartment). Voted but unscanne the bottom trunk section of the black Ballot Transfer to secure them for transport and document the number of the black ballot Transfer to secure them for transport and document the number of the black ballot box and p transfer to secure them for transport and document the number of the black ballot box and p transfer ballot box and p transfer bag (top compartment).	d ballots are to be placed in Bag. Place a seal on the bag	
5. Repack all <u>unused</u> ballots into the same cardboard the cardboard box, secrecy sleeves, and extension co box and seal.	•	
6. All EViDs should be repacked with all power cords,	signature pads.	
7. All privacy booths should be disassembled and place found in the morning.	ed on the pallet as they were	
8. Any provisional ballots used will be kept in the blue the bag and document the number on the PRF Sectio tote.	<del>-</del>	
9. Clerk must complete Precinct Report Form. Call to 253-1450 after completion of the PRF to report to amount.		

u	10. Make sure when packing up, verify the items on the "Receipt for Election Supplies" go into the supply tote. All these items will be marked with bright stickers that say, "Return to Supply Tote." Take a quick inventory before you seal the supply tote for transport. Keep ALL USED SEALS — place all seals in labeled Ziploc in supply tote.
	11. Remember to bring ExpressVote, supply tote (including Provisional Ballot Bag), trifold signs, and black Ballot Transfer Bag to zone supply drop location.
	12. If you were issued a key to your polling place, make sure to put it in the top tray of the supply tote. Support staff will need the keys before 7:00 am the next morning to pick up equipment.
	13. Assign Election Workers to do a general cleanup of the polling place and return everything to the original condition prior to the election. Tables, chairs, food, garbage, etc.
	14. Make sure all precinct signs, cones, and posters are picked up from outside.

END

# XV. EViD Name and Address Changes

Precinct clerks can change a voter's name in the system, replacing the name on file with the name on the voter's ID. They can also make changes to the voter's residential address.

Note: A Refer to Clerk ticket is printed in Inspector mode if a voter requires a name or address change.

Only persons voting in the current election—either by regular ballot or by provisional ballot—can change their name and address via Fast Voter Check-in. If the voter is not eligible to vote in this election and they decline to vote provisionally, any name or address changes you make will not be saved in the system. You should advise ineligible voters that they should contact the elections office about any changes they want to make.

If you do not already have this dialog displayed, here's how to bring it up:

- 1. Search for the voter using ID swipe or Date of Birth lookup.
- On the Name and Address Verification dialog, touch No.
- Touch the Name/Address Change button.
- 4. Make the necessary changes and then touch **OK**.
- 5. Ask the voter to sign the signature pad.
- 6. Touch **Accept Signature**.
- 7. On the **Verify Voter Information** dialog, touch **Name/Address Change**.




#### Name and Residential Address Changes

#### To change a voter's residential address:

1. On the **Enter Voter Information** dialog, enter the voter's updated name, address, or both.

Name and address changes are made on the **Enter Voter Information** dialog.



- Touch Find Address to narrow down the exact residential address for the voter.
- If the voter's address has changed, you can easily clear all the address fields on the dialog by touching Clear Address.
- 2. Touch **OK** when all the information is updated. The system will then verify that the address is a valid residential address in your county.
  - If the address is valid, a voting certificate will print, indicating that the voter's name or address has changed.
  - If the address is invalid, you will see a message to that effect. Touch No to
    return to the Enter Voter Information dialog and verify with the voter that the
    address you entered is correct. If the system still will not accept the address,
    consult the Supervisor of Elections office.

#### **Searching for a Residence Address**

During the process of making an address change on a voter record, if you have trouble locating the address where the voter resides, the **Find Address** option enables you to search for the correct address using a street number and street name or street name only.

You do not need to enter the directional information (such as N, E, SE) or street type (ST, RD, and so on). For example, if the voter indicates his or her address is "2500 North Monroe Street," and the address is not found by performing a search from the **Update Address** dialog, you can enter *Monroe*, into the Find Residence Address field, and the system will return a list of all street names with the text "Monroe" present. From the results list, you can then select the correct street name. You can also enter the street number *2500*, in conjunction with the name *Monroe*, to narrow down the search results to segments of Monroe Street with a residential street number of 2500.

If no exact matches to the street name are found, the system will perform a search based on words that sound like the street name entered. For example, if you enter "Munrow" the system will return all the "Monroe" entries.

#### To use the Find Address feature to locate an address:

- 1. On the **Enter Voter Information** dialog, touch the **Find Address** button, located in the lower right corner of the dialog next to the Clear Address field.
- 2. On the **Find Residence Address** dialog, enter the street number and street name or simply the street name. Do not enter prefixes, suffixes, or street types.



3. The search results appear in a grid of matching street names, like the one shown on next page.

N Monroe St, Anytown, FL 12301	N Monroe St, Picture Perfect, FL 12308	N Monroe St, Anytown, FL 12312	S Monroe St, Anytown, FL 12301	

- 4. Notice in figure above there are several instances of *Monroe St.* You will see multiple listings like this when a street has segments in more than one zip code. Be sure to pay close attention to the street segment you select, based on the information that the voter has provided. Select the voter's street on the grid. The correct street name and zip code are entered on the **Enter Voter Information dialog**. Continue with step 5 below.
- 5. To narrow the search results, touch **Cancel** on the grid to return to the **Find Residence Address** dialog. You can enter the residence street number in conjunction with the street name. See the figure below for an example.



The search results are narrowed down to streets with the name Monroe with a number 2500.

N Monroe St, NewTown, FL 32312	S Monroe ST Anytown, FL 32301			
	Plantwood St. Anytown, F1 12301			
Page 1 of 1	1	1	1	Cancel

6. Select the voter's street on the grid. The number and correct street name and zip code are entered on the Enter Voter Information dialog.

Note: In Inspector mode, a Refer to Clerk ticket is printed for a voter who wants to change their name or address.

- 7. Check to make sure all the fields on the **Enter Voter Information** dialog are filled in and touch **OK** to save the changes to the system.
- 8. Complete a Multi-Purpose Form.


**Note:** Never change a Mailing Address – have voter contact office.

#### **Signature Update**

Complete a Multi-Purpose Form to include a new signature.

## XVI. UNDO A CHECK-IN

When you Undo a Check-in, you can only undo a previous voter's check-in. If you must undo a voter check-in past the previous voter, you must call the Elections Office.



4) An Undo ticket will print. Paper clip the original Voting Pass and the Undo Ticket. Keep the Voting Pass and Undo Ticket segregated.


# XVII. APPENDIX



#### **MULTI-PURPOSE FORM**

s T	ATE OF FLORIDA			DE		_	TION T	_	_	CURE	_		ANCE			OHN.	TVC	F LAKE
	ite			-	CLA	``	non i	٠.	JL	COIL	73.	,,,,,,	AIICE		Precinct			LAKE
De																		
١, _	(Print name)																	
_	(Print name)	nd /	or_		(Pri	nt n	iame)		_	_ in vo	ting	at th	e	(Name	of election	h	eld	
on	(Date of election)				•													
٠.	,																	
Sig	gnature of Voter:						Swo	m a	an	a subs	cribe	d to	me tn	IIS	day	от		_, 20
Sig	gnature of Official Administ	erin	g Oa	ith: _					_									
ST	ATE OF FLORIDA			DEC	LAR	ΑT	ION TO	P	RO	OVIDE	ASS	ISTA	ANCE			COUN	ITY	OF LAKE
Da	ite													Pr	ecinct			
ï		br	ava h	oon	racus	o to	ad by								to provid	e him	or	
	(Print Name)	-			- 1		(Pr			me of V				stance)				
	r with assistance to vote. I ent of the union of the vote																	
10	0 feet of such locations in	an e	effort	to pr	rovide	as	sistano	e.							,	-		
Sig	gnature of Assistor:					Sı	wom an	d s	suk	oscribe	d to	me th	nis		day of		, 20	
Sir	anature of Official Administ	erin	n Oa	th														
_			_															
	s: New Registration Reco					Add					ame, S	Signatu	re) [	Reque	est to Repla SE ONLY	ce Vote	r Infor	mation Card
1	Are you a citizen of the United  I affirm I have never been of					_	☐ YES	_	_	NO			-					
	☐ If I have been convicted of	a felo	ony, I			ting	g rights h	ave	be be	een reste	ored b	у						
2	the Board of Executive Cle	a felo	ony, I a	affirm	my vo	ting	rights h	ave	be	en resto	red		l					
	pursuant to s. 4 , Art. VI of my sentence, including par					upc	n the co	mpl	leti	on of all	terms	s of	FVR	S No:				
3	☐ I affirm that I have not been	ı adj	udicat	ed m	entally	inc	apacitate	d w	vith	respect	to vo	ting o	r, if I h	ave, my	right to vo	te has	been	restored.
4	Date of Birth (MM-DD-YYYY	1			-			-	L									
_	Florida Driver License (FL DL)	or F	lorida	ident	ificatio	n (I	L ID) Car	rd N	lun	nber			If no DL o		Last 4 digit Security No		cial	I have
5	П П - Г	П		٦.		Г	٦ - ٢		T		٦.	Г	ID, th provi	nen 🔽				these numbers.
6	Last Name				_		First Na	me	,		_	_	Mi	ddle Na	me		ne Su	
7	Address Where You Live (lega	resi	dence-	no P.	O. Box	)	Apt/Lot/	Unit	t	City					County	1		Code
8	Mailing Address (if different from	n ab	ove ad	idress	;)	_	Apt/Lot/	Unit	t	City					State or C	ountry	Zip	Code
_	Address Where You Were Las	Pac	iletere	d to 1	foto	_	Apt/Lot/	Lleit		City					State		7ie	Code
9			,,,,,,,,,,		-010		l '			-							Ι.	
10	0 Former Name (if name is changed) Gender State or Country of Birth Telephone No. (optional)					al)												
11	☐ Email me SAMPLE BALLO' (See Public Record Notice above						my coun	ty.										
	y Affiliation				(Checi		ly one)	(	Ch	eck only	one if	applic	able)					D I will
(Che	ck only one. If left blank, you will gistered without party affiliation)				dian/Ala		n Native	1	اٍ¤	am an a Marine n	ctive o	duty U	niform	ed Serv	ices or Mei	chant		need assistance
<b>□</b> F	lorida Democratic Party				r isiand Hispar		Origin	10					lepend	ent of a	n active dut	y unifor	med	with voting.
	epublican Party of Florida to party affiliation		Hispar		4111	-1- 4	04-1-	١.		services								□ I am
	linor party (print party name):		wnite, Multi-ri		fHispai	nic (	Ungin	ľ	_	am a U.	S. citi	zen re	siding	outside	the U.S.			interested in becoming a
	Oath: I do solemnly sweet (or effirm		Other:	whood	_		_											poll worker.
	end defend the Constitution of the U the Constitution of the State of Fi	Inted	States	and	SIGI	ĸ												Date
12	qualified to register as an elector unde end lews of the State of Florida, and t	or the	Constit	ution	HER													
	provided in this application is true.	-				~												
		- 1		<b>A</b>	.14:		<b>.</b>	_			_							

#### Multi-Purpose Form



# PRECINCT REPORT FORM AM (Return to Binder)

Election: 2027 PPP Precinct\_\_105/828\_

SECTION 1 (C	CLERK) <mark>Initial each seal</mark>	How Many?	Outgoi	ng Seals	Initials
Supply Tote		1			
<b>Provisional Ba</b>	llot Certificates Issued	30	0000	0792	
EViD Serial #	E055-18B00317	1	232	323	
EViD Serial #	E055-18B00317	1	424	242	
EViD Serial #	E055-18B00317	1	108	801	
EViD Serial #					
EViD Serial #					
EVID THUMB DRIVES		3	Installe	ed 1 ea.	
Verizon Jetpack MiFi (Found in Clerk EVID)		1			

**Precinct Report Form** Front Side

SECTION 2 (Ballot Issuer)		Number of ballots issued Piece 1 Piece 2		Ballot Issuer Initials	Electio Initi	
Ballot Style	G015	500	N/A			
Ballot Style	G171	500	N/A			
Ballot Style			N/A			
Ballot Style			N/A			
Ballot Style			N/A			
Ballot Style			N/A			

1000

SECTION 3 (TEC	H) <mark>Initial each</mark>	serial & seal			
ExpressVote Serial #	A.M.	Seal #	Blank Ballo	ExpVt. Thumb	
EV011637****	0000	5113	20	1	
DS200 Serial #	Top Hatch Seal #	Ballot Box Seal #	Auxiliary Seal # (Do not remove)	Thumb Drive Seal #	Thumb Drive Serial # (Cannot verify)
ES010738****	00005051	00005052	00002031	000015	16A
ES010738****	00005386	00005374	00002030	000324	16B

We certify that the ballot styles/ranges received have been verified; all seals have been verified and the ballot box has been emptied and locked prior to opening of the polls at 7:00 am.

CLERK:	WITNESS:
Print Name	Print Name
Comments	

Rev. 06/17/20

Key Set for DS200/ExpressVote

# PRECINCT REPORT FORM PM (Return to Binder)

Election: 2027 PPP Precinct\_\_105/828\_

SECTION 4 (TEC	н)			
DS200 Serial #	Top Hatch Seal #	Ballot Box Seal #	ExpressVote Cards	Public Count
ES010738****				
ES010738****				+
*A		Total	Public Count:	=

**Precinct Report Form** Back Side

		UNUSED I	BALLOTS
SECTION 5 (BALLO	OT ISSUER)	Piece 1	Piece 2
Ballot Style	G015		N/A
Ballot Style	G171	+	N/A
	*B TOTALS	=	

SECTION 6 (CLERK)				
If numbers do not match please explain (i.e. Express Vote Cards u	Do these 2	numbers match?		
DS200 Public Count (enter number from total DS200s)	*A			EViD Grand Total
Unused Ballots (ballots leftover / not used)	*B	+		•
Provisional Ballots (count amount from Provisional Log)	С	+		
Spoiled Ballots (count amount from Spoiled Log)	D	+		
	SUM	=	1000	Total Ballots from SOE
If numbers do not match please explain (i.e. Express Vote Cards us	sed):	•		
		Do these 2	numbers match?	

SECTION 7 (CLER	K)						Clerk Int.
DS20	Must ma	atch total in Sec. 3-Place	e in Ziplo	ck			
ExpressVote Thumb Drive		Must ma	atch total in Sec. 3-Place	in Ziplo	ck	1	
EVID Activator Thumb Drives		Must mo	atch total in Sec. 1-Place	in Ziplo	ck		
Pro	visional Ballot Bag		Record Seal Number			Seal #	
Supply Tote Seal		Record Seal Number			Seal #		
Black Ballot Transfer Bag	Bag 1 Seal #		Bag 2 Seal #		Bag	3 Seal #	

We the undersigned C	lerk and Witness of this voting precinct do HEREBY CERTIFY that the preceding
	form has been completed in its entirety:
CLERK:	WITNESS:

Signature / Phone

Signature / Phone

## RECEIPT FOR ELECTION SUPPLIES Precinct\_

# Have this document <u>in hand and ready</u> for Receiving Attendant. Each line should be initialed before leaving the polling place.

If an item on this list is not checked or missing the Receiving Attendant will direct the Clerk to return to the polling place and retrieve that item. Upon arrival at Election Central a complete inventory will take place. If an item is not found, a phone call will follow.

Clerk and Witness Initial Below	
/ Circle (1, 2, 3) BLACK BALLOT TRANSFER BAG(S) <u>SEALED and Documented on PRF</u>	
/Supply Tote <u>SEALED and Documented on PRF</u>	
/ Provisional Ballot Certificate Bag <u>SEALED and Documented on PRF</u> (In Tote)	
/ Verizon Jetpack for EViD's. <u>DO NOT</u> put back in the EViD container as found. (Tote Top)	
/ Ziplock bag w/ DS200, ExpressVote <u>Thumb Drive(s), Zero and Totals Tapes</u> (Tote Top)	
/ Ziplock bag w/ EViD Thumb Drives (Tote Top)	
/Ziplock bag with ALL EViD tickets (Tote Top)	Receipt for Election Supplies
/ Emergency Precinct Registers (In Tote)	
/ Affirmation Folder (In Tote) Used Documents in Back Pocket	
/Clerk Binder (In Tote)	
/ Payroll Sheets ( <u>Return in Clerk Binder</u> ) Ensure all have signed	
/ Precinct Report Form ( <u>Return in Clerk Binder</u> ) Completely Filled Out w/ Signatures	
/Keys for DS200 ( <u>Return in Clerk Binder</u> )	
/ ExpressVote with privacy screen	
/ Tri-fold information signs (2)	
/Other	
Date	
Clerk Print Name (1 <sup>st</sup> ) Clerk Phone	
Witness Print Name (2 <sup>nd</sup> )	
Departure Time from Precinct	
•	
Transfer of Custody	
Arrival Time at Zone Supply Drop Location All Seals Intact? Circle – Y / N	
Receiving Attendant (Print Name)	
Notes:	

(Blue Copy to Precinct Clerk)

Ver.4.2019